



Installing Projectory 1.0 for UNIX/Linux/BSD/Mac OS X

**Corey Ehmke
Project Lead
Updated 2/9/2004**

This document provides instructions for installing Projectory 1.0 on a Mac or PC running a distribution of UNIX, Linux, BSD, or Mac OS X with the Apache web server.

After installing, please refer to the document "Getting Started with Projectory 1.0" for configuration and usage information.

If you need additional help with installation or configuration, please refer to the support information at <http://projectory.sourceforge.net/support/>

Step 1: Install MySQL

1. Download and install MySQL 4.x from <http://www.mysql.com/>
2. If you are installing on Mac OS X, we recommend the MySQL installer available from Marc Liyanage at <http://www.entropy.ch/software/macosx/mysql/>
3. Follow the installation procedures for your flavor of *NIX
4. Make sure that MySQL is configured to automatically start at boot-up.

Step 2: Configure MySQL

1. Set the root password

```
[~/]: mysql -u root
```

```
mysql> UPDATE user SET Password=PASSWORD("your password")
      WHERE user="root";
```

2. Create an empty database for Projectory

```
mysql> create database projectory_db;
```

3. Create a user account for Projectory

```
mysql> grant all on projectory_db.* to projectory@localhost
      identified by "projectory password";
```

```
mysql> exit;
```

Step 3: Create the Projectory database

1. Locate the file projectory_db_init.sql
2. Use it to create the stub Projectory database

```
[~/]: mysql -u root -p projectory_db <
      /path/to/install/directory/projectory_db_init.sql
```

Step 4: Install the Projectory Web Application

1. Locate the file `projectory.cgi` and the folder `projectory_images`
2. Copy them to the desired location within the web site root folder (e.g. `/wwwroot/projectory/`)
3. Make sure that Perl is installed and configured on the server
4. Use CPAN (`sudo perl -MCPAN -e shell`) to install all necessary Perl modules:
 - `Date::Manip`
 - `DBI`
 - `DBD::MySQL`
 - `Crypt::Rijndael`
5. Be sure to change the default password used to connect to the MySQL database in `setGlobalParams` in `projectory.cgi`.

Step 5: Configure Apache to Recognize Projectory

1. Open the Apache configuration file using `sudo pico /etc/httpd/httpd.conf` (or `vi` or whatever)
2. Make sure that this line is uncommented:

```
LoadModule cgi_module libexec/httpd/mod_cgi.so
```
3. Make sure that this line is uncommented:

```
AddModule mod_cgi.c
```
4. In the Document Types section, after `<IfModule mod_mime.c>`, uncomment

```
AddHandler cgi-script .cgi
```

5. Add these lines after the `DocumentRoot` directory entry.

```
<Directory "/wwwroot/projectory/">
    Options ExecCGI
    AddHandler cgi-script cgi
    AllowOverride Options
    Order allow,deny
    Allow from all
</Directory>
```

6. If Projectory is installed somewhere else in your web root, adjust the lines above accordingly.
7. Restart Apache using `sudo apachectl restart`

Step 6: Test Your Installation

1. Access Projectory through a web browser. If you installed it in a folder called `projectory` in the web root of your server, the URL will be `http://your_server_address/projectory/projectory.cgi`
2. If you see a dump of Projectory's source code, or get a server error, then you have not correctly configured Apache to run CGI at the location where Projectory is installed.

Step 7: Configure Projectory

1. Please see the document "GettingStarted with Projectory" for information on configuring Projectory.